

[illegible]

001
001
001
001
001
001
001
001
7FF
7FF
7FF
7FF
7FF
7FF
7FF
7FF
7FF

[illegible]

```
0001 0 %TITLE 'SMG$$PRVINP - Private Input support routines'
0002 0 MODULE SMG$$PRVINP (
0003 0 IDENT = '1-001' ! File: SMGPRVINP.B32 Edit: STAN1001
0004 0 ) =
0005 1 BEGIN
0006 1
0007 1 *****
0008 1 *
0009 1 * COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0010 1 * DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0011 1 * ALL RIGHTS RESERVED.
0012 1 *
0013 1 * THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0014 1 * ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0015 1 * INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0016 1 * COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0017 1 * OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0018 1 * TRANSFERRED.
0019 1 *
0020 1 * THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0021 1 * AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0022 1 * CORPORATION.
0023 1 *
0024 1 * DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0025 1 * SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0026 1 *
0027 1 *****
0028 1
0029 1
```



```

31 0030 1  ++
32 0031 1  FACILITY:      Screen Management
33 0032 1
34 0033 1  ABSTRACT:
35 0034 1      The procedures in this module act as interfaces between the
36 0035 1      virtual displays and pasteboards and associated data structures, and
37 0036 1      the keyboard input side of SMG.  These routines are called to pass
38 0037 1      information about changes to the physical screen that have been
39 0038 1      brought about by input-related activities.
40 0039 1      These are in a module by themselves so that they can be explicitly
41 0040 1      linked into programs that need them (like WHAT) since they
42 0041 1      will not be in the SMGSHR vector.
43 0042 1
44 0043 1  ENVIRONMENT:  User mode, Shared library routines.
45 0044 1
46 0045 1  AUTHOR: R. Reichert, CREATION DATE: 9-Mar-1983
47 0046 1
48 0047 1  MODIFIED BY:
49 0048 1
50 0049 1  1-001 - Original.  Moved out of other modules. STAN 7-Mar-1984.
51 0050 1  --

```

```
53 0051 1 XSBTTL 'Declarations'
54 0052 1
55 0053 1 SWITCHES:
56 0054 1
57 0055 1
58 0056 1
59 0057 1 LINKAGES:
60 0058 1
61 0059 1 NONE
62 0060 1
63 0061 1 TABLE OF CONTENTS:
64 0062 1
65 0063 1
66 0064 1 FORWARD ROUTINE
67 0065 1
68 0066 1 ! Private entry points:
69 0067 1
70 0068 1 SMG$$INVALIDATE_DISPLAY, ! Mark contents of display as unknown
71 0069 1
72 0070 1 SMG$$REPORT_CHANGE_INSERT, ! Report change to physical
73 0071 1 ! screen in insert mode.
74 0072 1
75 0073 1 SMG$$REPORT_CHANGE_REPLACE; ! Report change to physical
76 0074 1 ! screen in replac mode.
77 0075 1
78 0076 1
79 0077 1 INCLUDE FILES
80 0078 1
81 0079 1
82 0080 1 REQUIRE 'RTLIN:SMGPROLOG'; ! defines psects, macros, tcb,
83 0158 1 ! wcb, & terminal symbols
84 0159 1
85 0160 1
86 0161 1 EXTERNAL REFERENCES
87 0162 1
88 0163 1
89 0164 1 EXTERNAL
90 0165 1 PBD_L_COUNT, ! No. of pasteboards we currently have
91 0166 1
92 0167 1 PBD_A_PBCB : VECTOR [PBD_K_MAX_PB, LONG],
93 0168 1 ! Table of addresses of PBCB's
94 0169 1
95 0170 1 PBD_V_PB_AVAIL : BITVECTOR [PBD_K_MAX_PB];
96 0171 1 ! Bit vector of pasteboard id numbers in use.
97 0172 1
98 0173 1 EXTERNAL ROUTINE
99 0174 1 LIB$GET_VM, ! Allocate heap storage
100 0175 1
101 0176 1 SMG$INSERT_CHARS, ! Insert char in virtual display buffer
102 0177 1 ! and cause output.
103 0178 1
104 0179 1 SMG$$FILL_WINDOW_BUFFER, ! Map all virtual display buffers to
105 0180 1 ! the window buffer for a given PBCB
106 0181 1
107 0182 1 SMG$$FLUSH_BUFFER, ! Flush any pending output to terminal
108 0183 1
109 0184 1 SMG$$FORCE_SCROLL_REG, ! Force scroll region to specified
```

```

110 0185 1 ! lines.
111 0186 1
112 0187 1 SMG$LOCATE_PP, ! Locate pasting packet that joins a virtual
113 0188 1 ! display to a pasteboard.
114 0189 1
115 0190 1 SMG$MOVE_TEXT_TO_SCREEN_BUF,
116 0191 1
117 0192 1 SMG$MOVE_TEXT_TO_WINDOW_BUF, ! Map single virtual display to
118 0193 1 ! window buffer.
119 0194 1
120 0195 1 SMG$OCCLUDE, ! Determine overlap between two rectangular
121 0196 1 ! areas.
122 0197 1 SMG$MIN_UPD, ! Minimum output routine
123 0198 1
124 0199 1 SMG$PUT_TEXT_TO_BUFFER; ! Text to virtual display buffer
125 0200 1
126 0201 1 EXTERNAL LITERAL
127 0202 1
128 0203 1 SMG$_FATERRLIB, ! Fatal error in library procedure
129 0204 1 SMG$_INVARG, ! Invalid argument
130 0205 1 SMG$_INVCOL, ! Invalid column number
131 0206 1 SMG$_INVDIS_ID, ! Invalid virtual display id
132 0207 1 SMG$_INV?AS_ID, ! Invalid pasteboard id
133 0208 1 SMG$_INVROW; ! Invalid row number

```



```

135 0209 1 ZSBTTL 'SMG$$INVALIDATE_DISPLAY - Mark display as being privately used'
136 0210 1 GLOBAL ROUTINE SMG$$INVALIDATE_DISPLAY ( DISPLAY_ID) =
137 0211 1
138 0212 1 ++
139 0213 1 FUNCTIONAL DESCRIPTION:
140 0214 1
141 0215 1 This routine is called when ever a change has been completed
142 0216 1 to a given virtual display and the user had previously
143 0217 1 written into that display on his own, without using
144 0218 1 SMG routines.
145 0219 1
146 0220 1 The virtual display must not be occluded.
147 0221 1
148 0222 1 Each pasteboard to which this display is pasted is isolated and
149 0223 1 its window image must be redrawn.
150 0224 1 The new physical pasteboard cursor position gets set.
151 0225 1
152 0226 1 CALLING SEQUENCE:
153 0227 1
154 0228 1 ret_status.wlc.v = SMG$$INVALIDATE_DISPLAY ( DISPLAY_ID.rl.r )
155 0229 1
156 0230 1 FORMAL PARAMETERS:
157 0231 1
158 0232 1 DISPLAY_ID.rl.r Display ID of virtual display.
159 0233 1
160 0234 1 IMPLICIT INPUTS:
161 0235 1
162 0236 1 NONE
163 0237 1
164 0238 1 IMPLICIT OUTPUTS:
165 0239 1
166 0240 1 NONE
167 0241 1
168 0242 1 COMPLETION STATUS:
169 0243 1
170 0244 1 SS$ _NORMAL Normal successful completion
171 0245 1
172 0246 1 SIDE EFFECTS:
173 0247 1
174 0248 1 NONE
175 0249 1 --

```

```
177 0250 2 BEGIN
178 0251
179 0252 LOCAL
180 0253
181 0254 DCB : REF BLOCK [ ,BYTE], ! Addr of display control block
182 0255 CURR_PP : REF BLOCK [ ,BYTE], ! Addr of pasting packet under
183 0256 ! inspection
184 0257
185 0258 STATUS; ! Status of subroutine calls
186 0259
187 0260 !+
188 0261 ! This routine is independent of buffering.
189 0262 !-
190 0263
191 0264 $SMG$GET_DCB (.DISPLAY_ID, DCB); ! Get DCB address
192 0265
193 0266 CURR_PP = .DCB [DCB_A_PP_NEXT]; ! Start of chain of pasting
194 0267 ! packets to which this display
195 0268 ! is pasted.
196 0269
197 0270 !+
198 0271 ! Deal with each pasteboard that this virtual display is pasted to...
199 0272 !-
200 0273
201 0274 WHILE .CURR_PP NEQ DCB [DCB_A_PP_NEXT]
202 0275 DO
203 0276 BEGIN ! Overall loop
204 0277
205 0278 LOCAL
206 0279 PBCB : REF BLOCK [ ,BYTE], ! Address of pasteboard control
207 0280 WCB : REF BLOCK [ ,BYTE], ! Address of window control block
208 0281 TO_INDEX; ! Index into destination
209 0282
210 0283 PBCB = .CURR_PP [PP_A_PBCB_ADDR]; ! Select this pasteboard and WCB
211 0284 WCB = .PBCB [PBCB_A_WCB]; ! whose window needs rebuilding.
212 0285
213 0286 TO_INDEX = .CURR_PP [PP_W_TO_INDEX];
214 0287
215 0288 INCR R FROM 1 TO .CURR_PP [PP_W_ROWS_TO_MOVE]
216 0289 DO
217 0290 BEGIN ! For all rows in this display
218 0291 !+
219 0292 ! Zero out the display buffer.
220 0293 !-
221 0294 CH$FILL (0,
222 0295 .CURR_PP [PP_W_MOVE_LENGTH],
223 0296 .WCB [WCB_A_SCR_TEXT_BUF] + .TO_INDEX);
224 0297
225 0298 TO_INDEX = .TO_INDEX + .WCB [WCB_W_NO_COLS];
226 0299 END; ! For all rows to move
227 0300
228 0301 CURR_PP = .CURR_PP [PP_A_NEXT_DCB]; ! Walk the DCB side of
229 0302 ! the chain from front
230 0303 ! to back.
231 0304
232 0305 END; ! Overall loop
233 0306 2 RETURN SS$NORMAL
```


SMG\$\$PRVINP
1-001

SMG\$\$PRVINP - Private Input support routines
SMG\$\$INVALIDATE_DISPLAY - Mark display as being

G 11

16-Sep-1984 01:10:09

14-Sep-1984 13:09:59

VAX-11 Bliss-32 V4.0-742
[SMGRTL.SRC]SMGPRVINP.B32;1

Page 7
(5)

: 234
: 235

0307 2
0308 1 END;

! End of routine SMG\$\$INVALIDATE_DISPLAY

.TITLE SMG\$\$PRVINP SMG\$\$PRVINP - Private Input support routines

.IDENT \1-001\

.EXTRN PBD_L_COUNT, PBD_A_PBCB
.EXTRN PBD_V_PB_AVAIL, [IB\$GET_VM
.EXTRN SMG\$INSERT_CHARS
.EXTRN SMG\$\$FILL_WINDOW_BUFFER
.EXTRN SMG\$\$FLUSH_BUFFER
.EXTRN SMG\$\$FORCE_SCROLL_REG
.EXTRN SMG\$\$LOCATE_PP, SMG\$\$MOVE_TEXT_TO_SCREEN_BUF
.EXTRN SMG\$\$MOVE_TEXT_TO_WINDOW_BUF
.EXTRN SMG\$\$OCCLUDE, SMG\$\$MIN_UPD
.EXTRN SMG\$PUT_TEXT_TO_BUFFER
.EXTRN SMG\$_FATERRLIB, SMG\$_INVARG
.EXTRN SMG\$_INVCOL, SMG\$_INVDIS_ID
.EXTRN SMG\$_INVPAS_ID, SMG\$_INVROW

.PSECT _SMG\$CODE, NOWRT, SHR, PIC, 2

.ENTRY SMG\$\$INVALIDATE_DISPLAY, Save R2,R3,R4,R5,- : 0210
R6,R7,R8,R9,R10,R11

MOVL @DISPLAY_ID, R0 : 0264
CML 56(R0), @DISPLAY_ID

BNEQ 1\$
CMPB 68(R0), #17
BEQL 2\$
MOVL #SMG\$_INVDIS_ID, R0

RET
MOVL @DISPLAY_ID, DCB : 0266

MOVL 32(DCB), -CURR_PP : 0274
MOVAB 32(DCB), R0

CML CURR_PP, R0
BEQL 6\$: 0283

MOVL 20(CURR_PP), PBCB : 0284
MOVL 8(PBCB), WCB

MOVZWL 32(CURR_PP), TO_INDEX : 0286
MOVZWL 28(CURR_PP), R1T : 0288

CLRL R : 0298
BRB 5\$

MOVC5 #0, (SP), #0, 34(CURR_PP), @20(WCB)- : 0296
[TO_INDEX]

MOVZWL 6(WCB), R0 : 0298
ADDL2 R0, TO_INDEX

AOBLEQ R1T, R, 4\$: 0288
MOVL (CURR_PP), CURR_PP : 0301

BRB 3\$: 0274
MOVL #1, R0 : 0306

RET : 0308

; Routine Size: 93 bytes, Routine Base: _SMG\$CODE + 0000

```
237 0309 1 %SBTTL 'SMG$$REPORT_CHANGE_INSERT - Report change to screen -- insert'
238 0310 1 GLOBAL ROUTINE SMG$$REPORT_CHANGE_INSERT (
239 0311 1     DISPLAY_ID,
240 0312 1     PASTEBOARD_ID,
241 0313 1     CHANGED_CHAR,
242 0314 1     CHANGED_ROW,
243 0315 1     CHANGED_COL,
244 0316 1     TERMINATING_CHAR
245 0317 1 ) =
246 0318 1
247 0319 1 ++
248 0320 1 FUNCTIONAL DESCRIPTION:
249 0321 1     This routine is called to report a change made to the physical
250 0322 1     screen via an input action involving insertion. The character
251 0323 1     identified by CHANGED_CHAR has been positioned on the screen in
252 0324 1     a position corresponding to the virtual display coordinates
253 0325 1     CHANGED_ROW and CHANGED_COL.
254 0326 1
255 0327 1     TERMINATING_CHAR specifies the details of the change.
256 0328 1
257 0329 1     If TERMINATING_CHAR has not been specified, then CHANGED_CHAR
258 0330 1     has been echoed in the position indicated. The original
259 0331 1     contents of the line from CHANGED_COL to the right-hand edge of
260 0332 1     the virtual display need to be shifted to the right by one
261 0333 1     character. The new contents of CHANGED_COL+1 through the
262 0334 1     right-hand edge need to be redisplayed on the screen.
263 0335 1     Current cursor position is changed to reflect that one beyond
264 0336 1     that indicated by CHANGED_COL. If this new position is now
265 0337 1     beyond the bounds of the virtual display's dimensions
266 0338 1     then ??????.
267 0339 1
268 0340 1     If TERMINATING_CHAR was specified, CHANGED_CHAR has been echoed
269 0341 1     in the position indicated. Furthermore, this character was
270 0342 1     followed by a TERMINATING_CHAR. The original contents of the
271 0343 1     line from CHANGED_COL to the right-hand edge of the virtual
272 0344 1     display need to be shifted to the right by one character. The
273 0345 1     new contents of CHANGED_COL+1 through the right-hand edge need
274 0346 1     to be redisplayed on the screen.
275 0347 1     Current cursor position is changed to reflect the effects of
276 0348 1     the TERMINATING_CHAR. If this new position is now beyond the
277 0349 1     bounds of the virtual display's dimensions then ????.
278 0350 1
279 0351 1 CALLING SEQUENCE:
280 0352 1
281 0353 1     ret_status.wlc.v = SMG$$REPORT_CHANGE_INSERT (
282 0354 1         DISPLAY_ID.rl.r,
283 0355 1         PASTEBOARD_ID.rl.r,
284 0356 1         CHANGED_CHAR.rb.r,
285 0357 1         CHANGED_ROW.rl.r,
286 0358 1         CHANGED_COL.rl.r,
287 0359 1         [,TERMINATING_CHAR.rb.r])
288 0360 1
289 0361 1 FORMAL PARAMETERS:
290 0362 1
291 0363 1     DISPLAY_ID.rl.r      Display id of virtual display.
292 0364 1     PASTEBOARD_ID.rl.r   Pasteboard id.
293 0365 1
```

```
294 0366 1 | CHANGED_CHAR.rb.r The character that modified the screen.
295 0367 1 |
296 0368 1 | CHANGED_ROW.rl.r Row number within the virtual display in
297 0369 1 | which CHANGED_CHAR was written.
298 0370 1 |
299 0371 1 | CHANGED_COL.rl.r Column number within the virtual display
300 0372 1 | where CHANGED_CHAR was written.
301 0373 1 |
302 0374 1 | [,TERMINATING_CHAR.rb.r] [Optional].
303 0375 1 | If supplied, the terminating character
304 0376 1 | that followed CHANGED_CHAR (See
305 0377 1 | functional description for meaning).
306 0378 1 |
307 0379 1 | IMPLICIT INPUTS:
308 0380 1 |
309 0381 1 | NONE
310 0382 1 |
311 0383 1 | IMPLICIT OUTPUTS:
312 0384 1 |
313 0385 1 | NONE
314 0386 1 |
315 0387 1 | COMPLETION STATUS:
316 0388 1 |
317 0389 1 | SSS NORMAL Normal successful completion
318 0390 1 | SMG$_INVDIS_ID Invalid Display Id
319 0391 1 | SMG$_INVPAS_ID Invalid Pasteboard Id
320 0392 1 | SMG$_INVROW Invalid row specified
321 0393 1 | SMG$_INVCOL Invalid column specified
322 0394 1 |
323 0395 1 | SIDE EFFECTS:
324 0396 1 |
325 0397 1 | NONE
326 0398 1 |
327 0399 1 |
328 0400 2 | BEGIN
329 0401 2 | BUILTIN
330 0402 2 | NULLPARAMETER;
331 0403 2 |
332 0404 2 | LOCAL
333 0405 2 | DESC : BLOCK [8,BYTE], | Local descriptor
334 0406 2 | STATUS, | Status of subroutine calls
335 0407 2 | DCB : REF $DCB_DECL, | Addr of display control block
336 0408 2 | PBCB : REF $PBCB_DECL, | Addr of pasteboard control
337 0409 2 | | block.
338 0410 2 | PP : REF $PP_DECL; | Addr of pasting packet
339 0411 2 |
340 0412 2 | SSMG$VALIDATE_ARGCOUNT (5, 6); | Test for right no. of args
341 0413 2 |
342 0414 2 | +
343 0415 2 | Get addresses of control blocks we need
344 0416 2 | -
345 0417 2 | SSMG$GET_DCB (.DISPLAY_ID, DCB); | Get DCB addr.
346 0418 2 | SSMG$GET_PBCB (.PASTEBOARD_ID, PBCB); | Get PBCB addr.
347 0419 2 | IF NOT (STATUS = SMG$LOCATE_PP (.DCB, .PBCB, PP)) | Get PP addr.
348 0420 2 | THEN
349 0421 2 | RETURN (.STATUS);
350 0422 2 |
```



```

351 0423 2 SSMG$VALIDATE_ROW_COL (..CHANGED_ROW, ..CHANGED_COL); ! Valid Pos.?
352 0424 2
353 0425 2
354 0426 2 + Initialize our local descriptor to point to the changed character.
355 0427 2 -
356 0428 2 DESC [DSCSW_LENGTH] = 1;
357 0429 2 DESC [DSCSB_CLASS] = DSCSK_CLASS_S;
358 0430 2 DESC [DSCSB_DTYPE] = DSCSK_DTYPE_T;
359 0431 2 DESC [DSCSA_POINTER] = .CHANGED_CHAR;
360 0432 2
361 0433 2 +
362 0434 2 Reflect this change in the virtual display text and attribute buffer,
363 0435 2 including new virtual display cursor position.
364 0436 2 Data from the affected column to the last-1 column of this line need
365 0437 2 to be moved one character position to the right and the changed
366 0438 2 character inserted at the indicated position. The attributes for the
367 0439 2 moved bytes must be moved as well.
368 0440 2 -
369 0441 2 IF NOT (STATUS = SMG$INSERT_CHARS ( .DISPLAY_ID,
370 0442 2 .CHANGED_ROW,
371 0443 2 .CHANGED_COL,
372 0444 2 DESC))
373 0445 2 THEN
374 0446 2 RETURN (.STATUS);
375 0447 2
376 0448 2 IF NOT NULLPARAMETER (6)
377 0449 2 THEN
378 0450 2 BEGIN ! Terminator supplied
379 0451 2 +
380 0452 2 Inspect supplied terminator to determine effect on cursor
381 0453 2 position in virtual display.
382 0454 2 -
383 0455 2 +
384 0456 2 ***** For now pretend the terminator is a <CR>. *****
385 0457 2 ***** This needs to act like a <CR><LF> pair.
386 0458 2 -
387 0459 2 IF NOT (STATUS = SMG$SPUT_TEXT_TO_BUFFER (
388 0460 2 .DCB,
389 0461 2 .DCB [DCB_B_DEF_VIDEO_ATTR],
390 0462 2 1
391 0463 2 XREF (CR*8 + LF), ! <CR><LF>
392 0464 2 .DCB [DCB_B_DEF_CHAR_SET]))
393 0465 2 THEN
394 0466 2 RETURN (.STATUS);
395 0467 2 END; ! Terminator supplied
396 0468 2
397 0469 2 +
398 0470 2 Reflect this change in the appropriate positions of the window screen
399 0471 2 text and attribute buffers, including new screen cursor position.
400 0472 2 -
401 0473 2 IF NOT (STATUS = SMG$MOVE_TEXT_TO_WINDOW_BUF ( .PP))
402 0474 2 THEN
403 0475 2 RETURN (.STATUS);
404 0476 2
405 0477 2 +
406 0478 2 Record what has happened to screen buffer as well.
407 0479 2 -

```

```
408 0480 3 IF NOT (STATUS = SMG$MOVE_TEXT_TO_SCREEN_BUF ( .PP))
409 0481 THEN
410 0482 RETURN (.STATUS);
411 0483
412 0484 !+
413 0485 Must now force the changes to be output.
414 0486 !-
415 0487 IF .PP [PP_W_ROWS_TO_MOVE] NEQ 0
416 0488 THEN
417 0489 BEGIN
418 0490 ! Assume damage confined to single row.
419 0491 PBCB [PBCB_W_FIRST_CHANGED_ROW] = ..CHANGED_ROW;
420 0492 PBCB [PBCB_W_LAST_CHANGED_ROW] = ..CHANGED_ROW;
421 0493
422 0494 ! Assume damage in row from given pos. to end of line
423 0495 PBCB [PBCB_W_FIRST_CHANGED_COL] = ..CHANGED_COL;
424 0496 PBCB [PBCB_W_LAST_CHANGED_COL] = .PBCB [PBCB_W_WIDTH];
425 0497 END;
426 0498
427 0499 STATUS = SMG$MIN_UPD ( .PBCB);
428 0500
429 0501 !+
430 0502 If this virtual display is pasted to pasteboards other than the one
431 0503 identified in the call list, these additional pasteboard's window
432 0504 buffers must be updated as well. For these additional pasteboards,
433 0505 the changed byte in addition to the shifted remainder of the line
434 0506 must be output -- since they did not receive the originally echoed
435 0507 character.
436 0508 !-
437 0509 PP = .DCB [DCB_A_PP_NEXT]; ! 1st in chain
438 0510 WHILE .PP NEQ DCB [DCB_A_PP_NEXT] ! While any packets remain...
439 0511 DO
440 0512 BEGIN ! Loop through all pasting packets for this DCB
441 0513 LOCAL
442 0514 NEW_PBCB : REF $PBCB_DECL; ! PBCB being considered
443 0515
444 0516 NEW_PBCB = .PP [PP_A_PBCB_ADDR]; ! PBCB for this packet
445 0517 IF .NEW_PBCB NEQ .PBCB ! If this isn't the one we started with
446 0518 THEN
447 0519 BEGIN ! Needs to be output
448 0520 IF NOT (STATUS = SMG$FILL_WINDOW_BUFFER (.NEW_PBCB))
449 0521 THEN
450 0522 RETURN (.STATUS);
451 0523
452 0524 IF .PP [PP_W_ROWS_TO_MOVE] NEQ 0
453 0525 THEN
454 0526 BEGIN
455 0527 ! Assume damage confined to single row.
456 0528 PBCB [PBCB_W_FIRST_CHANGED_ROW] = ..CHANGED_ROW;
457 0529 PBCB [PBCB_W_LAST_CHANGED_ROW] = ..CHANGED_ROW;
458 0530
459 0531 ! Assume damage in row from given pos. to end of line
460 0532 PBCB [PBCB_W_FIRST_CHANGED_COL] = ..CHANGED_COL;
461 0533 PBCB [PBCB_W_LAST_CHANGED_COL] = .PBCB [PBCB_W_WIDTH];
462 0534 END;
463 0535
464 0536 IF NOT (STATUS = SMG$MIN_UPD ( .NEW_PBCB))
```

```

465 0537 4 THEN
466 0538 RETURN (,STATUS);
467 0539 END; ! Needs to be output
468 0540
469 0541 PP = .PP [PP_A_NEXT_DCB]; ! Step to next packet in chain
470 0542 END; ! Loop through all pasting packets for this DCB
471 0543
472 0544 RETURN (SS$_NORMAL);
473 0545 END; ! End of routine SMG$REPORT_CHANGE_INSERT

```

				01FC 00000		.EXTRN SMG\$_WRONUMARG		
						.ENTRY	SMG\$REPORT_CHANGE_INSERT, Save R2,R3,R4,-	0310
							R5,R6,R7,R8	
						MOVAB	SMG\$MIN_UPD, R8	
						SUBL2	#16, SP	
						SUBB3	#5, (AP), DIFF	0412
						CMPB	DIFF, #1	
						BLEQU	1\$	
						MOVL	#SMG\$_WRONUMARG, R0	
						RET		
						MOVL	@DISPLAY_ID, R0	0417
						CMPL	56(R0), @DISPLAY_ID	
						BNEQ	2\$	
						CMPB	68(R0), #17	
						BEQL	3\$	
						MOVL	#SMG\$_INVDIS_ID, R0	
						RET		
						MOVL	@DISPLAY_ID, DCB	
						MOVL	@PASTEBOARD_ID, R0	0418
						BLSS	4\$	
						CMPL	R0, PBD_L_COUNT	
						BGTR	4\$	
						BBS	R0, PBD V PB_AVAIL, 5\$	
						MOVL	#SMG\$_INVPAS_ID, R0	
						RET		
						MOVL	PBD_A_PBCB[R0], PBCB	
						PUSHAB	PP	0419
						PUSHL	PBCB	
						PUSHL	DCB	
						CALLS	#3, SMG\$LOCATE_PP	
						BLBC	STATUS, 10\$	
						MOVL	CHANGED_ROW, R6	0423
						TSTL	(R6)	
						BLEQ	6\$	
						CMPZV	#0, #16, 2(DCB), (R6)	
						BGEQ	7\$	
						MOVL	#SMG\$_INVROW, R0	
						RET		
						MOVL	CHANGED_COL, R7	
						TSTL	(R7)	
						BLEQ	8\$	
						CMPZV	#0, #16, 6(DCB), (R7)	
						BGEQ	9\$	
						MOVL	#SMG\$_INVCOL, R0	

08	AE	010E0001	8F	D0	000A1	98:	RET		0428
0C	AE	0C	AC	D0	000A2		MOVL	#17694721, DESC	0431
		08	AE	9F	000AF		MOVL	CHANGED_CHAR, DESC+4	0441
	7E		56	7D	000B2		PUSHAB	DESC	0442
		04	AC	DD	000B5		MOVQ	R6, -(SP)	0443
00000000G	00		04	FB	000B8		PUSHL	DISPLAY_ID	0444
	42		50	E9	000BF		CALLS	#4, SMG\$INSERT_CHARS	
	06		6C	91	000C2		BLBC	STATUS, 128	
			24	1F	000C5		CMPB	(AP), #6	0448
		18	AC	D5	000C7		BLSSU	118	
			1F	13	000CA		TSTL	24(AP)	
	7E	30	A4	9A	000CC		BEQL	118	0464
04	AE	0D0A	8F	3C	000D0		MOVZBL	48(DCB), -(SP)	0463
		04	AE	9F	000D6		MOVZWL	#3338, 4(SP)	
			01	DD	000D9		PUSHAB	4(SP)	
	7E	2E	A4	9A	000DB		PUSHL	#1	0459
			54	DD	000DF		MOVZBL	46(DCB), -(SP)	0461
00000000G	00		05	FB	000E1		PUSHL	DCB	0460
	5F		50	FB	000E8	108:	CALLS	#5, SMG\$PUT_TEXT_TO_BUFFER	
	53	04	AE	D0	000EB	118:	BLBC	STATUS, 158	0459
			53	DD	000EF		MOVL	PP, R3	0473
00000000G	00		01	FB	000F1		PUSHL	R3	
	7D		50	E9	000F8		CALLS	#1, SMG\$MOVE_TEXT_TO_WINDOW_BUF	
			53	DD	000FB		BLBC	STATUS, 198	
00000000G	00		01	FB	000FD		PUSHL	R3	0480
	71		50	E9	00104	128:	CALLS	#1, SMG\$MOVE_TEXT_TO_SCREEN_BUF	
		1C	A3	B5	00107		BLBC	STATUS, 198	
			15	13	0010A		TSTW	28(R3)	0487
00A8	C2		66	B0	0010C		BEQL	138	
00AA	C2		66	B0	00111		MOVW	(R6), 168(PBCB)	0491
00AC	C2		67	B0	00116		MOVW	(R6), 170(PBCB)	0492
00AE	C2	5A	A2	B0	0011B		MOVW	(R7), 172(PBCB)	0495
			52	DD	00121	138:	MOVW	90(PBCB), 174(PBCB)	0496
	68		01	FB	00123		PUSHL	PBCB	0499
04	AE	20	A4	D0	00126		CALLS	#1, SMG\$MIN_UPD	
	53	04	AE	D0	0012B	148:	MOVL	32(DCB), PP	0509
	51	20	A4	9E	0012F		MOVL	PP, R3	0510
	51		53	D1	00133		MOVAB	32(DCB), R1	
			3D	13	00136		CMPB	R3, R1	
	55	14	A3	D0	00138		BEQL	188	
	52		55	D1	0013C		MOVL	20(R3), NEW_PBCB	0516
			2E	13	0013F		CMPB	NEW_PBCB, PBCB	0517
			55	DD	00141		BEQL	178	
00000000G	00		01	FB	00143		PUSHL	NEW_PBCB	0520
	2B		50	E9	0014A	158:	CALLS	#1, SMG\$FILL_WINDOW_BUFFER	
		1C	A3	B5	0014D		BLBC	STATUS, 198	
			15	13	00150		TSTW	28(R3)	0524
00A8	C2		66	B0	00152		BEQL	168	
00AA	C2		66	B0	00157		MOVW	(R6), 168(PBCB)	0528
00AC	C2		67	B0	0015C		MOVW	(R6), 170(PBCB)	0529
00AE	C2	5A	A2	B0	00161		MOVW	(R7), 172(PBCB)	0532
			55	DD	00167	168:	MOVW	90(PBCB), 174(PBCB)	0533
	68		01	FB	00169		PUSHL	NEW_PBCB	0536
	09		50	E9	0016C		CALLS	#1, SMG\$MIN_UPD	
04	AE		63	D0	0016F	178:	BLBC	STATUS, 198	
			B6	11	00173		MOVL	(R3), PP	0541
							BRB	148	0510

SMG\$\$PRVINP	SMG\$\$PRVINP - Private Input support routines	N 11	16-Sep-1984 01:10:09	VAX-11 Bliss-32 V4.0-742	Page 14
1-001	SMG\$\$REPORT_CHANGE_INSERT - Report change to sc		14-Sep-1984 13:09:59	[SMGRTL.SRC]SMGPRVINP.B32;1	(6)
	50	01	00 00175 18\$:	MOVL #1, R0	: 0544
		04	00178 19\$:	RET	: 0545
: Routine Size: 377 bytes, Routine Base: _SMG\$CODE + 005D					
: 474 0546 1 !<BLF/PAGE>					

```
476 0547 1 %SBTTL 'SMG$$REPORT_CHANGE_REPLACE - Report change to screen -- replace'
477 0548 1 GLOBAL ROUTINE SMG$$REPORT_CHANGE_REPLACE (
478 0549 1     DISPLAY_ID,
479 0550 1     PASTEBOARD_ID,
480 0551 1     NUM_CHARS : REF VECTOR [,WORD],
481 0552 1     CHANGED_CHARS : REF VECTOR [,BYTE],
482 0553 1     CHANGED_ROW,
483 0554 1     CHANGED_COL,
484 0555 1     TERMINATING_CHAR
485 0556 1 ) =
486 0557 1
487 0558 1 ++
488 0559 1 FUNCTIONAL DESCRIPTION:
489 0560 1
490 0561 1     This routine is called to report a change made to the physical
491 0562 1     screen via an input action involving replacement. The
492 0563 1     characters identified by CHANGED_CHARS and NUM_CHARS have been
493 0564 1     positioned on the screen in a position corresponding to the
494 0565 1     virtual display coordinates CHANGED_ROW and CHANGED_COL.
495 0566 1
496 0567 1     TERMINATING_CHAR specifies the details of the change.
497 0568 1
498 0569 1     If TERMINATING_CHAR has not been specified, then the changed
499 0570 1     characters have been echoed in the position indicated. No
500 0571 1     further output is required. Just need to update internal data
501 0572 1     bases to reflect that change. Current cursor position is
502 0573 1     changed to reflect that beyond the changed text. If this new
503 0574 1     position is now beyond the bounds of the virtual display's
504 0575 1     dimensions then ??????
505 0576 1
506 0577 1     If TERMINATING_CHAR was specified, the changed characters have
507 0578 1     been echoed in the positions indicated. Furthermore, these
508 0579 1     character were followed by a TERMINATING_CHAR. Just need to
509 0580 1     update internal data bases to reflect that change. Current
510 0581 1     cursor position is changed to reflect the effects of the
511 0582 1     TERMINATING CHAR. If this new position is now beyond the
512 0583 1     bounds of the virtual display's dimensions then ????.
513 0584 1
514 0585 1 CALLING SEQUENCE:
515 0586 1
516 0587 1     ret_status.wlc.v = SMG$$REPORT_CHANGE_REPLACE (
517 0588 1         DISPLAY_ID.rl.r
518 0589 1         PASTEBOARD_ID.rl.r,
519 0590 1         NUM_CHARS.rwu.r,
520 0591 1         CHANGED_CHARS.rab.r
521 0592 1         [,CHANGED_ROW.rl.r]
522 0593 1         [,CHANGED_COL.rl.r]
523 0594 1         [,TERMINATING_CHAR.rb.r])
524 0595 1
525 0596 1 FORMAL PARAMETERS:
526 0597 1
527 0598 1     DISPLAY_ID.rl.r      Display id of virtual display.
528 0599 1
529 0600 1     PASTEBOARD_ID.rl.r   Pasteboard id.
530 0601 1
531 0602 1     NUM_CHARS.rwu.r      The number of characters that changed.
532 0603 1
533 0604 1     CHANGED_CHARS.rab.r  Address of the characters that modified
534 0605 1     the screen.
```



```
533 0604 1 |
534 0605 1 |      CHANGED_ROW.rl.r      Row number within the virtual display in
535 0606 1 |                          which CHANGED_CHARS were written.
536 0607 1 |
537 0608 1 |      CHANGED_COL.rl.r      Column number within the virtual display
538 0609 1 |                          where CHANGED_CHARS were written.
539 0610 1 |
540 0611 1 |      [,TERMINATING_CHAR.rb.r] [Optional].
541 0612 1 |                          If supplied, the terminating character
542 0613 1 |                          that followed CHANGED_CHAR (See
543 0614 1 |                          functional description for meaning).
544 0615 1 |
545 0616 1 |      IMPLICIT INPUTS:
546 0617 1 |
547 0618 1 |          NONE
548 0619 1 |
549 0620 1 |      IMPLICIT OUTPUTS:
550 0621 1 |
551 0622 1 |          NONE
552 0623 1 |
553 0624 1 |      COMPLETION STATUS:
554 0625 1 |
555 0626 1 |          SS$ NORMAL      Normal successful completion
556 0627 1 |          SMG$_INVDIS_ID  Invalid Display Id
557 0628 1 |          SMG$_INVPAS_ID  Invalid Pasteboard Id
558 0629 1 |          SMG$_INVROW     Invalid row specified
559 0630 1 |          SMG$_INVCOL     Invalid column specified
560 0631 1 |
561 0632 1 |      SIDE EFFECTS:
562 0633 1 |
563 0634 1 |          NONE
564 0635 1 |      --
565 0636 1 |
566 0637 2 |      BEGIN
567 0638 2 |      BUILTIN
568 0639 2 |          NULLPARAMETER;
569 0640 2 |
570 0641 2 |      LOCAL
571 0642 2 |          STATUS,          | Status of subroutine calls
572 0643 2 |          C_ROW,           | Working row
573 0644 2 |          C_COL,           | Working col
574 0645 2 |          DCB : REF $DCB DECL, | Addr of display control block
575 0646 2 |          PBCB : REF BLOCK [,BYTE], | Addr of pasteboard control
576 0647 2 |                          | block.
577 0648 2 |          WCB : REF BLOCK [,BYTE], | Address of window block
578 0649 2 |          PP : REF BLOCK [,BYTE]; | Addr of pasting packet.
579 0650 2 |
580 0651 2 |      SSMG$VALIDATE_ARGCOUNT (4, 7);      ! Test for right no. of args
581 0652 2 |
582 0653 2 |      +
583 0654 2 |      Get addresses of control blocks needed.
584 0655 2 |      --
585 0656 2 |      SSMG$GET_DCB (,DISPLAY ID, DCB);      | Get DCB addr.
586 0657 2 |      SSMG$GET_PBCB (,PASTEBOARD ID, PBCB); | Get PBCB addr.
587 0658 2 |      IF NOT (STATUS = SMG$LOCATE_PP (,DCB, .PBCB, PP)) | Get PP addr.
588 0659 2 |      THEN
589 0660 2 |          RETURN (.STATUS);
```

```
590 0661
591 0662
592 0663 IF NOT NULLPARAMETER (5)
593 0664 THEN
594 0665 BEGIN
595 0666 C_ROW = ..CHANGED_ROW;
596 0667 DCB [DCB_W_CURSOR_ROW] = .C_ROW;
597 0668 END
598 0669 ELSE
599 0670 C_ROW = .DCB [DCB_W_CURSOR_ROW];
600 0671
601 0672 IF NOT NULLPARAMETER (6)
602 0673 THEN
603 0674 BEGIN
604 0675 C_COL = ..CHANGED_COL;
605 0676 DCB [DCB_W_CURSOR_COL] = .C_COL;
606 0677 END
607 0678 ELSE
608 0679 C_COL = .DCB [DCB_W_CURSOR_COL];
609 0680
610 0681 SSMG$VALIDATE_ROW_COL (.C_ROW, .C_COL); ! Valid posit?
611 0682
612 0683 !+ Reflect this change in the virtual display text and attribute buffers.
613 0684 !-
614 0685
615 0686
616 0687 !+ Invalidate physical cursor position.
617 0688 ! This will force output to begin with a direct cursor
618 0689 ! movement to the proper place.
619 0690 !-
620 0691
621 0692 WCB = .PBCB [PBCB A WCB];
622 0693 WCB [WCB_W_OLD_CUR_ROW] = 0;
623 0694 WCB [WCB_W_OLD_CUR_COL] = 0;
624 0695
625 0696 IF NOT (STATUS = SMG$PUT_TEXT_TO_BUFFER (
626 0697 .DCB,
627 0698 .DCB [DCB_B_DEF_VIDEO_ATTR],
628 0699 .NUM_CHARS[0],
629 0700 .CHANGED_CHARS,
630 0701 .DCB [DCB_B_DEF_CHAR_SET]))
631 0702 THEN
632 0703 RETURN (.STATUS);
633 0704
634 0705 IF NOT NULLPARAMETER (7)
635 0706 THEN
636 0707 BEGIN ! Terminator supplied
637 0708 !+
638 0709 ! Inspect supplied terminator to determine effect on cursor
639 0710 ! position in virtual display.
640 0711 !-
641 0712 IF NOT (STATUS = SMG$PUT_TEXT_TO_BUFFER (
642 0713 .DCB,
643 0714 .DCB [DCB_B_DEF_VIDEO_ATTR],
644 0715 !
645 0716 XREF (CR*8 + LF), ! <CR><LF>
646 0717 .DCB [DCB_B_DEF_CHAR_SET]))
```

```
647 0718 3      THEN
648 0719      RETURN (.STATUS);
649 0720      END;      ! Terminator supplied
650 0721
651 0722      +
652 0723      Reflect this change in the appropriate positions of the window
653 0724      text and attribute buffers, including new screen cursor position.
654 0725      -
655 0726      IF NOT (STATUS = SMG$MOVE_TEXT_TO_WINDOW_BUF ( .PP))
656 0727      THEN
657 0728      RETURN (.STATUS);
658 0729
659 0730      +
660 0731      Update screen buffers as well.
661 0732      -
662 0733      IF NOT (STATUS = SMG$MOVE_TEXT_TO_SCREEN_BUF ( .PP))
663 0734      THEN
664 0735      RETURN (.STATUS);
665 0736
666 0737      +
667 0738      If this virtual display is pasted to pasteboards other than the one
668 0739      identified in the call list, these additional pasteboard's window
669 0740      buffers must be updated as well. For these additional pasteboards,
670 0741      the changed bytes must be output -- since they did not receive the
671 0742      originally echoed characters.
672 0743      -
673 0744      PP = .DCB [DCB_A_PP_NEXT];      ! 1st in chain
674 0745      WHILE .PP NEQ DCB [DCB_A_PP_NEXT] ! While any packets remain...
675 0746      DO
676 0747      BEGIN      ! Loop through all pasting packets for this DCB
677 0748      LOCAL
678 0749      NEW_PBCB : REF $PBCB_DECL;      ! PBCB being considered
679 0750
680 0751      NEW_PBCB = .PP [PP_A_PBCB_ADDR];      ! PBCB for this packet
681 0752      IF .NEW_PBCB NEQ .PBCB ! If this isn't the one we started with
682 0753      THEN
683 0754      BEGIN      ! Needs to be output
684 0755      IF NOT (STATUS = SMG$FILL_WINDOW_BUFFER (.NEW_PBCB))
685 0756      THEN
686 0757      RETURN (.STATUS);
687 0758
688 0759      IF .PP [PP_W_ROWS_TO_MOVE] NEQ 0
689 0760      THEN
690 0761      BEGIN
691 0762      ! Assume damage confined to single row.
692 0763      NEW_PBCB [PBCB_W_FIRST_CHANGED_ROW] = .C_ROW;
693 0764      NEW_PBCB [PBCB_W_LAST_CHANGED_ROW] = .C_ROW;
694 0765
695 0766      ! Assume damage in row from given pos. to end of line
696 0767      NEW_PBCB [PBCB_W_FIRST_CHANGED_COL] = .C_COL;
697 0768      NEW_PBCB [PBCB_W_LAST_CHANGED_COL] =
698 0769      .NEW_PBCB [PBCB_W_WIDTH];
699 0770      END;
700 0771
701 0772      IF NOT (STATUS = SMG$MIN_UPD (.NEW_PBCB))
702 0773      THEN
703 0774      RETURN (.STATUS);
```



```

: 704      0775  4
: 705      0776
: 706      0777
: 707      0778      PP = .PP [PP_A_NEXT_DCB];      ! Step to next packet in chain
: 708      0779      END;      ! Loop-through all pasting packets for this DCB
: 709      0780
: 710      0781      RETURN (SS$_NORMAL);
: 711      0782      END;      ! End of routine SMG$REPORT_CHANGE_REPLACE

```

			01FC 00000		.ENTRY	SMG\$REPORT_CHANGE_REPLACE, Save R2,R3,R4,-	
	58	00000000G	00 9E 00002		MOVAB	R5,R6,R7,R8	0548
	5E		08 C2 00009		SUBL2	SMG\$PUT_TEXT_TO_BUFFER, R8	
50	6C		04 83 0000C		SUBB3	#8, SP	0651
	03		50 91 00010		CMPB	#4, (AP), DIFF	
			08 1B 00013		BLEQU	DIFF, #3	
	50	00000000G	8F D0 00015		MOVL	1\$	
			04 0001C		RET	#SMG\$_WRONUMARG, R0	
	50	04	BC D0 0001D	1\$:	MOVL	@DISPLAY_ID, R0	0656
04	BC	38	A0 D1 00021		CMPL	56(R0), @DISPLAY_ID	
			06 12 00026		BNEQ	2\$	
	11	44	A0 91 00028		CMPB	68(R0), #17	
			08 13 0002C		BEQL	3\$	
	50	00000000G	8F D0 0002E	2\$:	MOVL	#SMG\$_INVDIS_ID, R0	
			04 00035		RET		
	53	04	BC D0 00036	3\$:	MOVL	@DISPLAY_ID, DCB	
	50	08	BC D0 0003A		MOVL	@PASTEBOARD_ID, R0	0657
			11 19 0003E		BLSS	4\$	
	00000000G	00	50 D1 00040		CMPL	R0, PBD_L_COUNT	
			08 14 00047		BGTR	4\$	
08	00000000G	00	50 E0 00049		BBS	R0, PBD V PB_AVAIL, 5\$	
			50 00000000G	4\$:	MOVL	#SMG\$_INVPAS_ID, R0	
			04 00058		RET		
	55	00000000G	0040 D0 00059	5\$:	MOVL	PBD_A_PBCB[R0], PBCB	0658
		04	AE 9F 00061		PUSHAB	PP	
			28 BB 00064		PUSHR	#*M<R3,R5>	
00000000G	00		03 FB 00066		CALLS	#3, SMG\$LOCATE_PP	
	73		50 E9 0006D		BLBC	STATUS, 14\$	
	05		6C 91 00070		CMPB	(AP), #5	0662
			0F 1F 00073		BLSSU	6\$	
		14	AC D5 00075		TSTL	20(AP)	
			0A 13 00078		BEQL	6\$	
	56	14	BC D0 0007A		MOVL	@CHANGED_ROW, C_ROW	0665
28	A3		56 B0 0007E		MOVW	C_ROW, 40(DCB)	0666
			04 11 00082		BRB	7\$	0662
	56	28	A3 3C 00084	6\$:	MOVZWL	40(DCB), C_ROW	0669
	06		6C 91 00088	7\$:	CMPB	(AP), #6	0671
			0F 1F 0008B		BLSSU	8\$	
		18	AC D5 0008D		TSTL	24(AP)	
			0A 13 00090		BEQL	8\$	
	57	18	BC D0 00092		MOVL	@CHANGED_COL, C_COL	0674
2A	A3		57 B0 00096		MOVW	C_COL, 42(DCB)	0675
			04 11 0009A		BRB	9\$	0671

56	02	A3	57	2A	A3	3C	0009C	8\$:	MOVZWL	42(DCB), C_COL	0678
					56	D5	000A0	9\$:	TSTL	C_ROW	0680
					08	15	000A2		BLEQ	10\$	
			10		00	ED	000A4		CMPZV	#0, #16, 2(DCB), C_ROW	
					08	18	000AA		BGEQ	11\$	
			50	00000000G	8F	D0	000AC	10\$:	MOVL	#SMGS_INVROW, R0	
						04	000B3		RET		
					57	D5	000B4	11\$:	TSTL	C_COL	
					08	15	000B6		BLEQ	12\$	
57	06	A3	10		00	ED	000B8		CMPZV	#0, #16, 6(DCB), C_COL	
					08	18	000BE		BGEQ	13\$	
			50	00000000G	8F	D0	000C0	12\$:	MOVL	#SMGS_INVCOL, R0	
						04	000C7		RET		
			51	08	A5	D0	000C8	13\$:	MOVL	8(PBCB), WCB	0692
			24	A1	D4	000CC		CLRL	36(WCB)	0693	
			7E	30	A3	9A	000CF		MOVZBL	48(DCB), -(SP)	0701
			10	AC	DD	000D3		PUSHL	CHANGED_CHARS	0700	
			7E	0C	BC	3C	000D6		MOVZWL	#NUM_CHARS, -(SP)	0699
			7E	2E	A3	9A	000DA		MOVZBL	46(DCB), -(SP)	0698
					53	DD	000DE		PUSHL	DCB	0697
			68		05	FB	000E0		CALLS	#5, SMG\$\$PUT_TEXT_TO_BUFFER	
			63		50	E9	000E3	14\$:	BLBC	STATUS, 17\$	0696
			07		6C	91	000E6		CMPB	(AP), #7	0705
					20	1F	000E9		BLSSU	15\$	
				1C	AC	D5	000EB		TSTL	28(AP)	
					1B	13	000EE		BEQL	15\$	
			7E	30	A3	9A	000F0		MOVZBL	48(DCB), -(SP)	0717
04	AE	0DOA			8F	3C	000F4		MOVZWL	#3338, 4(SP)	0716
		04			AE	9F	000FA		PUSHAB	4(SP)	
					01	DD	000FD		PUSHL	#1	0712
			7E	2E	A3	9A	000FF		MOVZBL	46(DCB), -(SP)	0714
					53	DD	00103		PUSHL	DCB	0713
			68		05	FB	00105		CALLS	#5, SMG\$\$PUT_TEXT_TO_BUFFER	
			70		50	E9	00108		BLBC	STATUS, 21\$	0712
				04	AE	DD	0010B	15\$:	PUSHL	PP	0726
00000000G		00			01	FB	0010E		CALLS	#1, SMG\$\$MOVE_TEXT_TO_WINDOW_BUF	
		63			50	E9	00115		BLBC	STATUS, 21\$	
				04	AE	DD	00118		PUSHL	PP	0733
00000000G		00			01	FB	0011B		CALLS	#1, SMG\$\$MOVE_TEXT_TO_SCREEN_BUF	
		56			50	E9	00122		BLBC	STATUS, 21\$	
04	AE	20			A3	D0	00125		MOVL	32(DCB), PP	0744
		54			AE	D0	0012A	16\$:	MOVL	PP, R4	0745
		51			A3	9E	0012E		MOVAB	32(DCB), R1	
		51			54	D1	00132		CMPL	R4, R1	
					41	13	00135		BEQL	20\$	
		52		14	A4	D0	00137		MOVL	20(R4), NEW_PBCB	0751
		55			52	D1	0013B		CMPL	NEW_PBCB, PBCB	0752
					32	13	0013E		BEQL	19\$	
					52	DD	00140		PUSHL	NEW_PBCB	0755
00000000G		00			01	FB	00142		CALLS	#1, SMG\$\$FILL_WINDOW_BUFFER	
		2F			50	E9	00149	17\$:	BLBC	STATUS, 21\$	
				1C	A4	B5	0014C		TSTW	28(R4)	0759
					15	13	0014F		BEQL	18\$	
00AB	C2				56	B0	00151		MOVW	C_ROW, 168(NEW_PBCB)	0763
00AA	C2				56	B0	00156		MOVW	C_ROW, 170(NEW_PBCB)	0764
00AC	C2				57	B0	0015B		MOVW	C_COL, 172(NEW_PBCB)	0767
00AE	C2			5A	A2	B0	00160		MOVW	90(NEW_PBCB), 174(NEW_PBCB)	0769

SMG\$PRVINP
1-001

SMG\$PRVINP - Private Input support routines
SMG\$REPORT_CHANGE_REPLACE - Report change to s

H 12

16-Sep-1984 01:10:09
14-Sep-1984 13:09:59

VAX-11 Bliss-32 V4.0-742
[SMGRTL.SRC]SMGPRVINP.B32;1

Page 21
(7)

00000000G	00	52	DD	00166	18\$:	PUSHL	NEW_PCB	:	0772
	09	01	FB	00168		CALLS	#1, _SMG\$MIN_UPD	:	
04	AE	50	E9	0016F		BLBC	STATUS, 21\$:	
		64	D0	00172	19\$:	MOVL	(R4), PP	:	0778
		B2	11	00176		BRB	16\$:	0745
	50	01	D0	00178	20\$:	MOVL	#1, R0	:	0781
		04	0017B	21\$:		RET		:	0782

; Routine Size: 380 bytes, Routine Base: _SMG\$CODE + 01D6

; 712 0783 1 !<BLF/PAGE>

SMG\$\$PRVINP
1-001

I 12
16-Sep-1984 01:10:09

SMG\$\$PRVINP - Private Input support routines
SMG\$\$REPORT_CHANGE_REPLACE - Report change to s 14-Sep-1984 13:09:59

VAX-11 Bliss-32 V4.0-742
[SMGRTL.SRC]SMGPRVINP.B32;1

Page 22
(8)

: 714
: 715
: 716

0784 1 END
0785 1
0786 0 ELUDOM

! End of module SMG\$\$PRVINP

:

PSECT SUMMARY

:

Name

Bytes

Attributes

:

_SMG\$CODE

850 NOVEC,NOWRT, RD , EXE, SHR, LCL, REL, CON, PIC,ALIGN(2)

:

Library Statistics

:

File	----- Total	Symbols Loaded	----- Percent	Pages Mapped	Processing Time
-\$255\$DUA28:[SYSLIB]STARLET.L32;1	9776	9	0	581	00:01.0
-\$255\$DUA28:[SMGRTL.OBJ]RTLLIB.L32;1	36	0	0	8	00:00.1
-\$255\$DUA28:[SMGRTL.OBJ]SMGLIB.L32;1	469	38	8	38	00:00.4

:

COMMAND QUALIFIERS

:

BLISS/CHECK=(FIELD,INITIAL,OPTIMIZE)/NOTRACE/LIS=LIS\$:SMGPRVINP/OBJ=OBJ\$:SMGPRVINP MSRC\$:SMGPRVINP/UPDATE=(ENH\$:SMGPRVINP)

:

: Size: 850 code + 0 data bytes

: Run Time: 00:18.4

: Elapsed Time: 01:10.5

: Lines/CPU Min: 2557

: Lexemes/CPU-Min: 16151

: Memory Used: 162 pages

: Compilation Complete

0360 AH-BT13A-SE
VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION
CONFIDENTIAL AND PROPRIETARY